

Plop User's Manual

David Lewis, Mar 2021

Introduction


Plop is a GUI-based analysis and optimization program for mirror cells. It is based on the Plate program by Toshimi Taki, and enhanced to run hundreds of times faster, so that it can support optimization of the mirror cell by adjusting the design to minimize the wavefront error. It also supports the FEM program z88 (<https://en.z88.de/>) which is a powerful and excellent program for FEM analysis written by Prof. Dr.-Ing. Frank Rieg and his team. Plop uses a very old version of Z88 (v12) which is adequate for its purposes. Due to the complexity of Z88, I have not been able to perform the same level of speedup needed to perform optimization, so Z88 is only for analysis, not optimization. However, being a 3D model, its results are more accurate than Plate, and it can also analyze mirror cells that are tilted with respect to the ground, while Plate only performs analysis of horizontal mirror cells.

What exactly does analysis and optimization mean? Analysis means that Plop will perform a calculation of the mirror to determine the wavefront error at each point on the mirror due to gravity acting on it. Optimization allows Plop to move around the positions of the supports, including both the radius and angle, if specified, and even the relative amount of force on each point, to minimize the wavefront error. Plop can produce pictures with the dimensions of each of the cell components and their locations.


Plop contains a very general way of describing the mirror cell, but also has a design wizard that will handle almost all conventional cell designs.

Quick Start

After downloading and installing Plop, you should see it in your start menu under Gui Plop. The first time you start it you will see the What's New box. You can close this, and see it any time later under the Help menu item on the main page.



After closing this, you now see the main design form.



This form is the primary form for describing the mirror and starting other forms to run analysis or display results.

The majority of ATMs will be content with the Automatic Cell Design. This calls up a form that lets you select from a variety of commonly used cell designs.

Plop Cell Designer

File Run Graphic Plots Help

Automatic Cell Design

This quickly sets all parameters that you need for most common designs.
Use automatic cell design for a variety of common cell configurations.

Automatic Cell Design

Comments Mirror Size Obstructions and Holes Material Variables Cell Type Cell Design Edge Support and Tilt Cell Parts Basis Edit as Text

Diameter and Thickness

Diameter Fixed

Thickness Fixed

Focal Length

Form of focal length description

☐ Focal Length

☐ F-ratio

☐ Sagitta

☐ Relative Sagitta (sag/thick)

Focal Fixed

Now you will see the automatic cell design form. This lets you enter the basic parameters of mirror diameter, thickness, focal length, and size of the central hole, if any. Enter all of these parameters and click Next. In this example we'll use a typical 300mm f/5 mirror. Note that all dimensions are in mm.

Plop Automatic Cell Designer

Diameter of the mirror in millimeters	<input type="text" value="300"/>
Thickness of the mirror in millimeters	<input type="text" value="50"/>
Focal length of the mirror in millimeters	<input type="text" value="1500"/>
Diameter of the secondary mirror in millimeters	<input type="text" value="60"/>
Diameter of central hole, if any, else leave blank	<input type="text"/>

Now you can select the type of cell that you want to use from the list. Lets use a 6 point cell which is completely adequate for this 300mm diameter mirror. There also is a check button if you want to allow the angles of the cell supports to be changed as part of the optimization. For simple cells such as 3,6,9 points, all of the angles must be multiples of 120 degrees, so leave this unchecked, but for more complex cells it is possible to allow the angles to vary. So leave it unchecked and continue.

Plop Automatic Cell Designer

<p>Number of Points in the Cell</p> <p><input type="radio"/> 3 points</p> <p><input checked="" type="radio"/> 6 points</p> <p><input type="radio"/> 9 points</p> <p><input type="radio"/> 18 points</p> <p><input type="radio"/> 27 points</p> <p><input type="radio"/> 36 points</p> <p><input type="radio"/> 54 points</p> <p><input type="checkbox"/> Allow angles to vary</p>	<p>Select the cell style you want.</p> <p>Check if you want to allow the angles to be adjusted.</p>
---	---

When you click Done, the Plop run form will appear. This is also accessed from the main form under the Run menu item. The run form contains a number of check boxes, which you should leave alone for most optimizations. The one that deserves some explanation is the Refocus Error Calculation. Refocus means

that when Plop calculates the wavefront error, it will assume that the eyepiece is adjusted to best focus. This is because in many cases, especially for mirrors with a small number of supports, the mirror will sag in a way that is in part paraboloidal. The visual effects of this sag can be removed by the user adjusting the focus of the mirror slightly. Plop will take this into account when performing the analysis and optimization if this box is checked. The run form has a box that will tell you the amount of this refocus, but I removed the code to calculate it at some point while restructuring the code. I'll try and fix this.

Plop Run Controls

Graphic Plots

Plop P-V Error Num Trials Z88 P-V Error

Plop RMS Error Step Size Z88 RMS Error

Refocus change in focal length

Matrix Solution Progress

Run Plop | Zernike Polynomials | Monte Carlo | Trace

☒ Update pictures as optimization progresses

☒ Refocus Error Calculation

☐ Refocus Includes Tilt in Mirror

☐ Use P-V error for optimization (almost always a bad idea)

☒ Use Basis (automatic if none specified in edit sheet)

☐ Generate Z88 input after running Plop



Z88 Run Controls

Run Z88

Run Plop Controls

Start Plop Pause Resume Abort


Just click Start Plop. Or, you can select one or more of the graphic plots from the Graphic Plots menu before you start it, and watch Plop do the optimization. It will only take a second or two for a simple cell to be run, and you will see a popup when it is done. Click it to go back to the run form.




The run form now tells you the error on the mirror surface. Double this to get wavefront error. You can see that it has both RMS and P-V errors.

Note that Plop does not include any surface error that is obscured by the secondary mirror, and won't try to make the surface error smaller in this region. That's why the mirror cell design includes the secondary mirror size as one of its parameters.

Lets take a view of some of the plots we can see. Under the Graphic Plot menu item, there are lots of entries.




Click Color Plot to see a view of the surface deformation and a scale.




You can see how the mirror is high above the 6 support points, and low elsewhere. It also has a big depression in the center, since Plop doesn't attempt to reduce surface error where it doesn't matter.

You can see a diagram showing where the supports are located by using the Supports plot.




This is nice to look at, but doesn't have the information you need to build the cell. You need to use the Cell Parts and Part Dimensions plots. These will show a diagram of where the parts are, with labels on them, so you can refer between the two diagrams.





For our 6 point cell, there are 3 identical parts, which are bars. The distance between the points is shown as 86.304mm, and the center support is at 43.152. The plot also tells you where the center of the support should be located, both in polar and Cartesian coordinates. Note that there is a scrollbar on the part dimension form. You can use this to scroll between the various cell parts if there is more than one.

Using Z88


Using Z88 to analyze the mirror is optional. To do this you need to check the Generate X88 Input After Running Plop on the run form. This must be done before you run Plop. We could have done that originally, but we didn't, so check the box, then run Start Plop. It won't take as long because Plop has already optimized the cell. Now click the Run Z88 box.

The image shows a software window titled "Plop Run Controls". It has a standard Windows-style title bar with minimize, maximize, and close buttons. The window is divided into several sections. At the top, under the "Graphic Plots" tab, there are input fields for "Plop P-V Error" (5.02596e-06), "Num Trials" (35), "Z88 P-V Error" (1.82002e-06), "Plop RMS Error" (8.97036e-07), "Step Size" (0.000275462), and "Z88 RMS Error" (4.77935e-07). Below these is a "Refocus change in focal length" field set to 0 and a "Matrix Solution Progress" bar which is a horizontal row of 20 blue squares. A tabbed interface follows with "Run Plop" selected, and other tabs for "Zernike Polynomials", "Monte Carlo", and "Trace". Under the "Run Plop" tab, there are several checkboxes: "Update pictures as optimization progresses" (checked), "Refocus Error Calculation" (checked), "Refocus Includes Tilt in Mirror" (unchecked), "Use P-V error for optimization (almost always a bad idea)" (unchecked), "Use Basis (automatic if none specified in edit sheet)" (checked), and "Generate Z88 input after running Plop" (checked, circled in red). Below the checkboxes is a section labeled "Z88 Run Controls" containing a "Run Z88" button (circled in red). At the bottom, under "Run Plop Controls", are four buttons: "Start Plop", "Pause", "Resume", and "Abort".

Once this is done the error boxes for Z88 will also be loaded, and you can generate a graphic plot for the Z88 results as well. For smaller cells, Z88 will usually show a smaller surface deformation than Plate, but this is also more accurate. Plate's model of the mirror does not consider any compression of the thickness. Z88 models the mirror as a set of 3D regions, and models the forces in each of the 3 dimensions. We can visualize the difference by comparing the two diagrams below, showing how a single point support deforms the mirror. The Plate model treats the mirror as having no change in the thickness, while the Z88 model softens the peak above the support point. Thus, the Z88 analysis will show a smaller deformation, and is more accurate than Plate.




Now we take a look at the Z88 Color Plot and can visualize the softer peaks on the mirror surface.




The vertical scale is different from the previous picture (you can constrain the Z scale under the Options menu), but you can see less pronounced peakiness compared to the previous color plot.


A More Complex Example

Use Automatic Cell Designer to create a 600mm diameter, 50mm thickness, 3000mm F/L mirror with 120mm secondary and 18 points. Run Plop and view the color picture.



The parts diagram plot will now show the set of 3 bars and 6 triangles. Using the part dimension plot, you can scroll to see the exact dimensions and locations of the parts. Note the labels on each of the locations to help you orient the part with the overall design shown in the part diagram plot.





This should be enough for the vast majority of cell designers.

Z88 and Tilt